

# OUTLOOK POP3 VE IMAP KURULUMU

- [OUTLOOK POP3 VE IMAP KURULUMU](#)

# OUTLOOK POP3 VE IMAP KURULUMU

POP3: mailleri sunucudan bilgisayara indirir.

IMAP: mailleri sunucudan online görür, sunucudan indirmez.

(Denetim Masası - Mail bölümüne kadar tıklandıđı varsayılmıştır)

A- OUTLOOK POP3 KURULUMU:

**Add New Account**

**Internet E-mail Settings**  
Each of these settings are required to get your e-mail account working.

**User Information**

Your Name: Ad Soyad

E-mail Address: adsoyad@domainname.com

**Server Information**

Account Type: POP3

Incoming mail server: pop.domainname.com

Outgoing mail server (SMTP): smtp.domainname.com

**Logon Information**

User Name: adsoyad@domainname.com

Password: \*\*\*\*\*

☒ Remember password

☐ Require logon using Secure Password Authentication (SPA)

**Test Account Settings**

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings ...

☒ Test Account Settings by clicking the Next button

**Deliver new messages to:**

☒ New Outlook Data File

☐ Existing Outlook Data File

Browse

More Settings ...

< Back Next > Cancel

More Settings:

Internet E-mail Settings

General Outgoing Server Connection Advanced

☒ My outgoing server (SMTP) requires authentication

☒ Use same settings as my incoming mail server

☐ Log on using

User Name:

Password:

☒ Remember password

☐ Require Secure Password Authentication (SPA)

☐ Log on to incoming mail server before sending mail

OK Cancel

Internet E-mail Settings

General Outgoing Server Connection Advanced

Server Port Numbers

Incoming server (POP3):

☐ This server requires an encrypted connection (SSL)

Outgoing server (SMTP):

Use the following type of encrypted connection:  ▼

Server Timeouts

Short  Long 1 minute

Delivery

☒ Leave a copy of messages on the server

☒ Remove from server after  days

☐ Remove from server when deleted from 'Deleted Items'

OK Cancel

- OUTLOOK IMAP KURULUMU:

Add New Account

Internet E-mail Settings

Each of these settings are required to get your e-mail account working.

User Information

Your Name:Ad Soyad

E-mail Address:adsoyad@domainadi.com

Server Information

Account Type:IMAP

Incoming mail server:imap.domainadi.com

Outgoing mail server (SMTP):smtp.domainadi.com

Logon Information

User Name:adsoyad@domainadi.com

Password:\*\*\*\*\*

☒ Remember password

☐ Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings ...

☒ Test Account Settings by clicking the Next button

More Settings ...

< Back

Next >

Cancel

More Settings:

Internet E-mail Settings

General   **Outgoing Server**   Connection   Advanced

☒ My outgoing server (SMTP) requires authentication

☒ Use same settings as my incoming mail server

☐ Log on using

User Name:

Password:

☒ Remember password

☐ Require Secure Password Authentication (SPA)

☐ Log on to incoming mail server before sending mail

OK   Cancel

Internet E-mail Settings

General   **Sent Items**   Deleted Items

Outgoing Server   **Connection**   Advanced

Server Port Numbers

Incoming server (IMAP):

Use the following type of encrypted connection:  ▼

Outgoing server (SMTP):

Use the following type of encrypted connection:  ▼

Server Timeouts

Short  Long 1 minute

Folders

Root folder path:

OK   Cancel